

free pattern

Scotties on Parade








- DESIGNED BY BENARTEX
- FINISHED SIZE: 58" X 67"



© 2019 BENARTEX, LLC

CUTTING INSTRUCTIONS

WOF = Width of fabric | LOF = Length of fabric
**Sew strips via short ends, then subcut as indicated*

	A DOTTY FOR SCOTTIE 10x10 pack #DSC10PK	1 pack	(15) 10" squares, trim to (15) 7-1/2" squares
	B DOTTY FOR SCOTTIE BOXES 7885-12 Black	3/4 yd	(15) 7-1/2" squares, fussy cut
	C DOTTY FOR SCOTTIE STRIPE 7886-12 Black	2-1/4 yd	(4) 6" x LOF strips, Mitered Outer Border
	D DOTTY FOR SCOTTIE PLAID 7891-09 White	1-3/8 yd	(19) 2-1/2" x WOF strips; Sashing and Inner Border
	E DOTTY FOR SCOTTIE PLAID 7891-12 Black	1/2 yd	(7) 2-1/4" x WOF strips; Binding

QUILT CENTER ASSEMBLY

1 Sew (30) assorted 7-1/2" squares together with (24) D 2-1/2" x 7-1/2" sashing strips in rows according to Quilt Diagram.



2 Sew rows together with (5) D 2-1/2" x (43-1/2") sashing strips.

BORDER ASSEMBLY

Measure width and length of the quilt top to ensure border sizes, below are our cutting sizes.

3 INNER BORDER: Sew (1) D 2-1/2" x (52-1/2") strip to each side of quilt center.

4 INNER BORDER: Sew (1) D 2-1/2" x (47-1/2") strip to top and bottom of quilt center.

5 MITERED BORDER: Center (1) C 6" strip on (1) side of the quilt top and pin in place. Start sewing the stripe a 1/4" from the top edge of the quilt top and stop a 1/4" from the bottom edge. DO NOT TRIM THE EXCESS. Repeat with the opposite side.

6 Repeat Step 5 to sew (1) C 6" strip to the top and bottom of the quilt top, making sure to stop and start 1/4" away from each end of the quilt top. To miter each corner, fold the quilt top on a diagonal, wrong sides together. This should line up with the strips from the adjacent sides.

7 Starting at the sewn seam, draw a 45-degree line to the edge of the fabric. Sew on the drawn line. Trim the excess fabric leaving a 1/4" seam. Repeat this step with the remaining corners.

QUILT DIAGRAM (FINISHED SIZE: 58" X 67")



FINISHING: Cut batting and backing 3" larger than top on all sides. Layer backing, batting and top together and baste or pin. When quilting is completed, trim excess batting and backing. Bind as usual.

NOTE: If this Benartex pattern is included in a kit, any questions about the kit should be addressed to the vendor from whom you bought it.